How to Change the Proxy user for Salesforce

Last Modified on 03/25/2025 5:34 pm EDT

By default, Exalate sets the Salesforce user who installed the app as the Proxy user. However, you can change this user to fit your specifications.

First you'll need to create the user who will become the proxy user, keep in mind that this is the user that Exalate will use to update the tickets on behalf of the remote side of the integration.


You may also opt to use an API integration user as a proxy user, given that it has all the required permissions stated below:

Application Permissions:	Access unique user identifiers
	Perform requests at any time
	Manage Data Cloud Calculated Insight data
	Access Visualforce applications
	Access Headless Forgot Password API
	Access the identity URL service
	Manage Data Cloud profile data
	Manage Data Cloud Ingestion API data
	Access content resources
	Access Lightning applications
	Access Connect REST API resources
	Manage Data Cloud Identity Resolution
	Full access
	Perform segmentation on Data Cloud data
	Manage user data via Web browsers
	Access chatbot services
	Manage user data via APIs
	Perform ANSI SQL queries on Data Cloud data
	Manage Pardot services
	Access Analytics REST API Charts Geodata resources
	Access Headless Registration API
	Access Einstein GPT services
	Access all Data Cloud API resources
	Access Interaction API resources
	Access the Salesforce API Platform
	Access Analytics REST API resources
	Access custom permissions


Once you have created/chosen who will be the Proxy user you may assign the Exalate Admin permission set:

Assign Exalate Admin permission set


1. Go to Setup -> Users -> Permissions sets -> Exalate Admin.




2. Click Manage Assignments.




3. Click Add Assignments.



4. Select a user you want to give permissions to and click **Assign** to grant access to the Exalate console.




- 5. Click **Done**.
- 6. Go to your Exalate console and access the **General Settings** tab, then click on **Configure**:



7. On this window you will see the **Proxy User** field below:

Configure General Settings



Product

Glossarlogin page to login, the user who you log in with will become the new proxy user . API Reference ${\mathbb I}$

Security I

ON THIS PAGE

Pricing and Leansing

Resources
Subscribe for a weekly Exalate hack
Academy
Blog
YouTube Channel
Ebooks
Still need help?
Join our Community
Visit our Service Desk
Find a Partner
Find a Par