

Set up a Connection in Basic Mode for Jira Cloud

Last Modified on 01/15/2026 8:27 pm EST

Connections in Basic mode have a set of **Sync Rules**, generated by Exalate. You can sync a basic set of issue fields: summary, description, comments, attachments, and issue types.

Note that issue types are mirrored: tasks are synced as tasks, improvements as improvements, and so on. For example, when you sync epic Exalate creates either an issue with the default issue type, if the default issue type is set in the project configuration, or **Task** if not set. This also applies to any other issue type that is not found on the destination side.

All comments are synced as public comments.

Note: You cannot modify **Sync Rules** in Basic Mode.


If you want to edit/delete Sync Rules, you must upgrade the connection to Visual Mode or Script Mode.

Set up a Connection in Basic Mode from Jira Cloud

Note: It doesn't matter which side you start initiating the Connection from. The Exalate UI remains the same.

1. Navigate to the **Connections** tab in the Exalate console.

Click **Settings** → **Apps** & click **Connections** under the **Exalate** menu.



2. Click **Initiate connection**.

Connections

Connection defines synchronization behavior, including communication details, sync rules, and scope.

Initiate connection

Accept invitation



3. Enter the **Destination Instance URL**.

The **Destination Instance URL** is the link to the instance you want to set up a connection with. You can directly enter the link of that instance or the **Exalate URL** from the **General Settings** tab in the Exalate admin panel.

Note: If you enter the URL of your own instance here, Exalate determines it's a local connection between 2 projects within your instance.

Exalate suggests available Configuration Modes based on the destination instance.

4. Select **Basic**.

5. Click **Next**.

6. Select a project where you would like to sync entities received from the destination side.

Initiate connection ×

Select a project for the incoming sync

Exalate generates default sync rules to synchronize basic issue fields. By default the following issue data will be synchronized: summary, description, comments, attachments and issue types.

Please select the project where you want to create issues, received from the other side.*

Select Project

[< Previous](#) [Next](#)

7. Click **Next**.


8. Confirm if you have admin access to the destination instance.

Further steps are different if you have or don't have admin access to the destination instance.


- Select **Yes, I have admin access** if you have admin access to the destination instance. You are redirected to the destination instance to establish a connection.
- Select **No, I don't have admin access** if you don't have admin access to the destination instance. You generate an invitation for the destination instance admin so they could establish a connection on their end.

Initiate connection x

Do you have admin access to the destination instance?

 **Yes, I have admin access**

- You will be redirected to the destination instance to establish the connection

 **No, I don't have admin access**

- You will generate an invitation and send it to the destination instance admin to establish the connection

[< Previous](#)Initiate

Steps for: Yes, I have Admin Access

Click **Yes, I have admin access & Initiate** the connection.

Note: You are required to verify access on the destination instance. After which complete the following steps on the destination instance.

9. Select the project or repository where you want to sync entities.

Note: Selecting the project is not applicable to all platforms. In this case, the Connection is established after the previous step.

Accept invitation x

Select a project for the incoming sync

Exalate generates default sync rules to synchronize basic issue fields. You can adapt the sync rules later. By default the following issue data will be synchronized: summary, description, comments, labels and attachments.

Please select the project where you want to create entities, received from the other side.*

| v

[< Previous](#)Confirm

10. Click **Confirm**.

The Connection has been set up.

Note: Selecting the project is not applicable to all platforms. In this case, the Connection is established after the previous step.

Accept invitation ✕

Select a project for the incoming sync

After accepting an invitation for a Basic mode connection, Exalate will be able to sync basic issue fields. The sync rules cannot be updated. Exalate will sync the following issue data: summary, description, comments, and attachments.

Issue types are mirrored. This means that tasks will be synced as tasks, bugs as bugs, and improvements as improvements. If an issue type is not included in the basic set, it will be synced as a task.

Please select the project where you want to create entities, received from the other side.*

Select Project ▾

[← Previous](#) Confirm

14. Click **Confirm**.

The Connection has been set up.

Exalate ✕

Connection established successfully ✓

Sync your first issue to see how it works.

Please enter an issue key from the project **Test (TEST)** to proceed

TEST-1

[Product](#)

- [About Us](#)
- [Release History](#)
- [Glossary](#)
- [API Reference](#)
- [Security](#)

Exalate

[Pricing and Licensing](#)

Resources

[Subscribe for a weekly Exalate hack](#)

[Academy](#)

[Blog](#)

[YouTube Channel](#)

[Ebooks](#)

Still need help?

[Join our Community](#)

[Visit our Service Desk](#)

[Find a Partner](#)

