

Initiate a Connection in Script Mode for Salesforce


Last Modified on 03/13/2024 7:34 am EDT

Important: You cannot toggle between the different modes. To do so, you need to create a new Connection in Visual mode, Script mode, or Basic mode.


Initiate a Connection in Script Mode from Salesforce

Note: It doesn't matter which side you start initiating the Connection from. The Exalate UI remains the same. If you are initiating the connection you become the source and the other side becomes the destination.

1. Navigate to the **Connections** tab in Exalate



2. Click **Initiate Connection**.



3. Enter the **Destination Instance URL**.

The **Destination Instance URL** is the link to the instance you want to set up a connection with. You can directly enter the link of that instance or the **Exalate URL** from the **General Settings** tab in the Exalate admin panel.

Initiate connection

Destination instance URL ⓘ

https://example.exalate.net

I don't have a URL

Next

Exalate suggests available Configuration Modes based on the destination instance.

4. Select the Configuration Mode. In this case, **Script Mode**.


Initiate connection

Destination instance URL ⓘ


https://example.exalate.com

I don't have a URL


Choose the configuration type


Basic

- Automatic configuration of basic fields
- Sync rules cannot be edited
- Only Issues can be synced
- Recommended for use cases of basic complexity


Visual

- Low-code, visual interface
- Configure both sides of the connection using a single interface
- Recommended for use cases of basic to intermediate complexity


Script

- Groovy-based scripting
- Configure each side of the connection separately
- Recommended for use cases of basic to advanced complexity

Next

5. Click **Next**.

6. Enter the Connection Information

Field	Description
Local instance short name	A short name for your instance
Destination instance short name	A short name for the destination instance
Connection name	Name of the connection
Description	Description of the connection

Initiate connection

Connection information

Source side shortname*

Destination side shortname*

Connection name*

Description

< Previous

Initiate

7. Click **Initiate**.

8. Click **Copy invitation code**.

You can send the invitation code to the destination instance admin.

Initiate connection

On the "company B" side, you (or their application administrator) need to **Accept the Invitation**.

Use the following invitation code:

Copy invitation code

Done

9. Click **Go to remote** to access the destination instance.

Note: When the other side accepts your invitation your connection is activated. Refresh the **Connections** page to see the Connection status change.

Product

[About Us](#)

[Release History](#)

[Glossary](#)

[API Reference](#)

[Security](#)

[Pricing and Licensing](#)

Resources

[Academy](#)

[Blog](#)

[YouTube Channel](#)

[Ebooks](#)

Still need help?

[Join our Community](#) 

[Visit our Service Desk](#) 

[Find a Partner](#) 