Set Up a Connection in Visual Mode for Zendesk

Last Modified on 03/11/2024 9:07 am EDT

Important: You cannot toggle between the different modes. To do so, you need to create a new Connection in Visual mode, Script mode, or Basic mode.

Note: Before you set up a Connection in Visual mode ensure that:

- your instance is public.
- you have admin access to the destination instance.
- you are either in the Evaluation (trial) period or have a Paid license.

Initiate a Connection in Visual Mode from Zendesk

Note: It doesn't matter which side you start initiating the Connection from. The Exalate UI remains the same.

1. Navigate to the **Connections** tab in the Exalate console.

To navigate to the **Connections** tab:

1. Click **Exalate** in the list of apps.

4	+ Add						
♠	Dashboard						
2	Updates to your tickets	Open Tickets	(current)	Ticket Statistic	s (this week)		
* :	No recent updates.	1 YOU	523 GROUPS	0 GOOD	O BAD	0 SOLVED	
用		Tickets requ	iiring your at	ttention (501) <u>wh</u>	at is this?		
ul			ID S	Subject			
¢		Priority: Urg	jent				
Áy	Exalate		#81 T	est ticket			
			#83 D	Demo			

2. Click Connections.

2. Click Initiate Connection.

Connections			
Connection defines synchronization behavior, including communication details, sync rules, and scope.	Initiate connection	Accept invitation	2

3. Enter the **Destination Instance URL**.

The **Destination Instance URL** is the link to the instance you want to set up a connection with. You can directly enter the link of that instance or the **Exalate URL** from the **General Settings** tab in the Exalate admin panel.


Note: If you don't have the link,	toggle I don't	have a	URL. Ir	n this	case,	you a	re only	able to
set up a Connection in Script mo	de.							

	Initiate connection	on	×
Destination instance URL		l don't have a URL 🗸	
		Next	t

Exalate suggests available Configuration Modes based on the destination instance..

4. Select the Configuration Mode. In this case, Visual Mode.

Note: We are exploring ways to enhance or replace Visual Mode with an Al-Configuration mode for a better user experience. Check the **Beta** label added to the Visual mode screens. Your feedback is crucial, so let us know what you think.



5. Click Next.

6. Enter the Connection Information

Field	Description
Local instance short name	A short name for your instance
Destination instance short name	A short name for the destination instance
Connection name	Name of the connection
Description	Description of the connection

	Initiate connection	×
Connection information Local instance short name*	Remote instance short name*	
Connection name*		
Description		le
Previous	,	Vext

7. Click Next.

8. Click **Verify admin access** to confirm you have admin rights to the destination instance. Then click **Initiate**.

	Initiate connection	×
Exalate will establish a Visual mo	de connection with	uber .
	Verify admin access	

9. Click **Accept** to finish the verification process.


You see a pop-up window within the remote instance to finish the verification. You are also notified about the permissions that the destination instance user has.

The destination instance user has different permissions based on the platforms to be synced.

10. Click Initiate.

	Initiate connection	×
Ø	Verification confirmed. You can continue setting up the connection.	
Previous		Initiate

11. The Connection has been set up.





Conffgurevthe Connection in Visual Mode for Zendesk.

API Reference 🖸 Security 🖒 Pricing and Licensing 🖸 Resources Academy 🖒 Blog 🖍 YouTube Channel 🖸 Ebooks 🖒 Still need help? Join our Community 🗗 Visit our Service Desk Find a Partner 🖸