

# Initiate a Private Connection in Script Mode for Asana

Last Modified on 10/14/2025 11:50 pm EDT

## Note: For Private Connections:

- an instance you have access to is considered a public side.
- an instance you don't have access to is considered a private side: destination instance.

The main difference between private and public connection types is whether the HTTP/HTTPS requests are initiated from one side or from both sides. In this case, HTTP/HTTPS requests are initiated from the destination's private side only.

## Initiate a Private Connection from Asana

1. Navigate to the **Connections** tab in the Exalate console.
2. Click **Initiate Connection**.

### Connections

Connection defines synchronization behavior, including communication details, sync rules, and scope.

Initiate connection

Accept invitation



3. Click '**I don't have a URL**'

If the destination instance is in a private network toggle **I don't have a URL**.

Initiate connection

Destination instance URL ⓘ

https://example.exalate.net

I don't have a URL

☒

Next

4. Choose a **Script** connection mode and click **Next**.

Initiate connection

Destination instance URL ⓘ  

https://example.example.net

I don't have a URL ☒

Choose the configuration type

Basic

FREE PLAN ⓘ

- Automatic configuration of basic fields
- Sync rules cannot be edited
- Only tickets can be synced
- Recommended for use cases of basic complexity

AI ASSIST

Script

30-DAY TRIAL

- Groovy-based scripting
- Configure each side of the connection separately
- Recommended for use cases of basic to advanced complexity

Next

5. Enter Connection information & Click **Next**

Field	Description
Local instance short name	A short name for your instance
Destination instance short name	A short name for the destination instance
Connection name	Name of the connection
Description	Description of the connection

Initiate connection

Connection information

Local instance short name\*

Remote instance short name\*

?

Connection name\*

Description

< Previous


Next

9. Click **Next**.

**Note:** As this is a Public-Private connection and you don't have admin access to the other side, you can continue to configure on your end and then send an invitation to your partner.

## 10. Click **Copy Invitation Code**

Here you can copy the invitation code and send it over to your partner. The destination side is shown as "unknown" since this is a private side.



## 11. Click **Done**

Once your partner accepts the invitation, you can start synchronization.

### Product

[About Us](#)

[Release History](#)

[Glossary](#)

[API Reference](#)

[Security](#)

[Pricing and Licensing](#)

### Resources

[Subscribe for a weekly Exalate hack](#)

[Academy](#)

[Blog](#)

[YouTube Channel](#)

[Ebooks](#)

### Still need help?

[Join our Community](#)

[Visit our Service Desk](#)

[Find a Partner](#)

**Note:** When the connection is set up on the Public source side, the Private side administrator should accept the invitation in the Private-Public connection.