

Set Up a Connection in Visual Mode for Zendesk

Last Modified on 01/15/2026 8:17 pm EST

Important: You cannot toggle between the different modes. To do so, you need to create a new Connection in Visual mode, Script mode, or Basic mode.

Note: Before you set up a Connection in Visual mode ensure that:

- your instance is public.
- you have admin access to the destination instance.
- you are either in the Evaluation (trial) period or have a Paid license.

Initiate a Connection in Visual Mode from Zendesk


Note: It doesn't matter which side you start initiating the Connection from. The Exalate UI remains the same.

Note: We are exploring ways to enhance or replace Visual Mode with an AI-Configuration mode for a better user experience. Check the **Beta** label added to the Visual mode screens. Your feedback is crucial, [so let us know what you think](#).


1. Navigate to the **Connections** tab in the Exalate console.

To navigate to the **Connections** tab:

1. Click **Exalate** in the list of apps.



2. Click **Connections**.




2. Click **Initiate Connection**.



3. Enter the **Destination Instance URL**.

The **Destination Instance URL** is the link to the instance you want to set up a connection with. You can directly enter the link of that instance or the **Exalate URL** from the **General Settings** tab in the Exalate admin panel.

Note: If you don't have the link, click **I don't have a URL**. In this case, you are only able to set up a Connection in Script mode.



Exalate suggests available Configuration Modes based on the destination instance..

4. Select the Configuration Mode. In this case, **Visual Mode**.

Note: We are exploring ways to enhance or replace Visual Mode with an AI-Configuration mode for a better user experience. Check the **Beta** label added to the Visual mode screens. Your feedback is crucial, [so let us know what you think](#).

Initiate connection
✕

Destination instance URL ⓘ

✓

I don't have a URL

Choose the configuration type

Basic

- Automatic configuration of basic fields
- Sync rules cannot be edited
- Only Issues can be synced
- Recommended for use cases of basic complexity

BETA
Visual

- Low-code, visual interface
- Configure both sides of the connection using a single interface
- Recommended for use cases of basic to intermediate complexity

Script

- Groovy-based scripting
- Configure each side of the connection separately
- Recommended for use cases of basic to advanced complexity

Next

5. Click **Next**.

6. Enter the Connection Information

Field	Description
Local instance short name	A short name for your instance
Destination instance short name	A short name for the destination instance
Connection name	Name of the connection
Description	Description of the connection

Initiate connection
✕

Connection information

Local instance short name*

Remote instance short name*

?


Connection name*

Description

< Previous
Next

7. Click **Next**.

8. Click **Verify admin access** to confirm you have admin rights to the destination instance. Then click **Initiate**.




9. Click **Accept** to finish the verification process.


You see a pop-up window within the remote instance to finish the verification. You are also notified about the permissions that the destination instance user has.

The destination instance user has different permissions based on the platforms to be synced.

10. Click **Initiate**.



11. The Connection has been set up.



Configure the Sync (Scope)

1. Click **Configure Sync** to start configuring the connection.


You can even configure an existing connection by navigating to the **Connections** tab. Then click

the **Edit Connection**  icon in front of the Connection name.

2. **Select Project** on both sides.


Select the projects you want to use for the Connection, at both ends.

Note: Projects are not applicable to Zendesk in which case only the **Filter Entities** screen are visible.



3. Click **Filter entities** (Optional)

With this option, you can decide what information must be synchronized.



Set the **Filters**

You can also choose to have multiple filter options.

Filter example:

Status = Open, Hold
Type = Task
Priority = Urgent

In this case, the following combinations are synced:

- 1) Task with the Open status and Urgent priority
- 2) Task with the Hold status and Urgent priority

4. Set the **Sync Method**

Sync method

Automatic →	↓
Manual ←	↓

This option allows you to decide how information must be synced between the task management systems. You can choose from the following options:

Manual

The issue is synchronized manually.

Automatic

The issue is synchronized automatically based on the entities you have filtered in the previous step.

Disabled

The synchronization is disabled.

The arrows decide the direction of the synchronization.

5. Click **Next** to configure the field mappings.

Add the Field Mappings (Rules)

Rules denote the mapping between different entities & decide what must be synchronized. There are predefined default mappings for basic fields in every Visual mode Connection.

You can access these mappings by clicking **Next** after configuring the sync. The **Rules** section consists of these mappings.

company_A_to_company_B

Active

Back to Connections Publish

Scope Rules

Configure the synchronization behavior with the help of field mappings and script rules.

Expand all Collapse all + Add mapping

Order	company A	Sync direction	company B
1	Tags	↔	Labels
2	Type	↔	Issue type
3	State	↔	Status
4	Priority	↔	Priority
5	Title	↔	Summary
6	Description	↔	Description
7	Comments	↔	Comments

Note: The above is just an example of mapping. The actual mappings depend on the platforms under sync.

The top bar displays the local instance's short name and the remote instance's short name. These are the names you provided while setting up a connection.


It also has a **Sync direction**. The arrows indicate the direction, whether uni or bi-directional. You can choose to **Expand all** or **Collapse all** the mappings.

You can **Edit connection**  or **Delete mapping** . You can also drag and drop them, up or down to re-prioritize.

Edit Mappings

For instance, if you want to edit the Tags ↔ Labels mapping, click the **Edit mapping**  icon.

An **Edit mapping** dialog box opens.




The 'Edit mapping' dialog box is shown. It features a title bar 'Edit mapping'. Below the title bar, there are four dropdown menus arranged in a 2x2 grid. The top row contains 'company A*' (selected 'Labels'), 'Sync direction' (selected bidirectional arrow), and 'company B*' (selected 'Labels'). The bottom row contains 'If no matching value*' (selected 'Do nothing'). At the bottom right, there are 'Cancel' and 'Save' buttons.

Select the new fields to be mapped on both sides from the drop-down list. You can also edit the **Sync direction**. Sync direction allows you to control your sync in a specific direction, where the arrows indicate the direction.

Delete Mappings

You can delete a certain mapping if you don't want it.




The 'Delete mapping rule?' dialog box is shown. It has a red title bar with the text 'Delete mapping rule?' and a close icon. The main content area contains the text: 'You are about to delete the mapping rule. Synchronization of the field, based on this rule will stop.' At the bottom right, there are 'Cancel' and 'Delete' buttons.

Clicking the bin icon opens up a prompt to ensure you really want to delete the mapping. Click **Delete** to confirm the deletion.

Add New Mappings

To add a new mapping, click the **Add mapping** button.



The 'Add mapping' dialog box is shown. It has a title bar 'company A_to_company B' with 'Active' status. Below the title bar, there is a 'Back to Connections' button and a 'Publish' button. Below the title bar, there is a progress bar with 'Scope' and 'Rules' sections. Below the progress bar, there is a text box: 'Configure the synchronization behavior with the help of field mappings and script rules.' At the bottom, there are 'Expand all', 'Collapse all', and '+ Add mapping' buttons.

An **Add mapping** dialog box opens.

Add mapping

company A*

Sync direction

company B*

Cancel
Save

Select the required fields at both ends from a drop-down list. You can choose to keep the **Sync direction** as it is by default or edit it. Sync direction allows you to control your sync in a specific direction, where the arrows indicate the direction.

You can add sub-mappings by clicking the plus icon.

You can also specify what to do if the selected values do not match.

If no matching value *

Do nothing

Set a default value

Report an error

Do nothing

If no matching value *

If no matching value is found you can choose to:

Option	If the value doesn't exist
Set a default value	Fields are set to a default value you specify
Report an error	An error appears & is displayed on the Errors tab. The synchronization is blocked in this case.
Do nothing	The values stay the same

Save the changes whenever you are ready.

Custom field mappings

When you set up a Visual mode connection, Exalate fetches some of the custom fields for you. These are available through a drop-down list while adding a mapping.

If you don't find the custom field, there is always an option to add [Scripts](#).

The following are the supported custom field types:

Text:

- Jira Cloud: Text Field (multi-line), Text Field (single line)
- ADO: Text (single line), Text (multiple lines)
- Zendesk: Text, Multi-line, Date, Number, Decimal

Option:

- Jira Cloud: Radio Buttons, Select List (single choice)
- ADO: Picklist (string), Picklist (integer)
- Zendesk: Drop-down


User:

- Jira Cloud, on-prem: User Picker (single user)
- ADO: Identity
- Zendesk: - Not supported


Add Scripts for Advanced Configuration (Optional)

For advanced synchronization use cases, you can add Groovy Scripts to your Visual mode Connection.

To do so, click the arrow on the **Add Mapping** button. Select **Add Script**.



There is a default Script in the dialog box. You can edit it or simply delete the entire Script to start writing from scratch. Click **Save** when you finish adding the Scripts.



Script Syntax:

As a general rule of thumb, the Scripts follow the following syntax:

```
your_instance_shortcode.issue.customFields."your custom field name".value = remote.issue.customFields."remote custom field name"
```

Where,

1. your_instance_shortcode is the source instance.
2. remote_instance_shortcode is the destination instance.

These are the names you provided while setting up the Connection.

Initiate connection
✕

Connection information

Source side shortname*

Destination side shortname*

Connection name*

Description

< Previous
Initiate

3. This is followed by other issue properties, each separated with a "." operator.

Publish the Changes

To save the changes made to the **Scope** and **Rules** section and apply them to the Connection you have created, click **Publish**.

» company A_to_company B
Active
< Back to Connections
Publish

Scope
Rules

Configure the synchronization behavior with the help of field mappings and script rules.

Expand all
Collapse all
+ Add mapping

Order
company A
Sync direction
company B

Note: You can also use these hotkeys to publish a connection:

- Ctrl+S on Windows or Linux
- Cmd+S on Mac

Product

[About Us](#)

[Release History](#)

[Glossary](#) **Note:** Configuration changes made to the Connection are applied on the next synchronization.

[API Reference](#)

[Security](#)

[Pricing and Licensing](#)

Resources

[Subscribe for a weekly Exalate hack](#)

[Academy](#)

[Blog](#)

[YouTube Channel](#)

[Ebooks](#)

Still need help?

[Join our Community](#)

[Visit our Service Desk](#)

[Find a Partner](#)